

ubuntu - Podrška #14469

mraka-2 vista sp1 grub multiboot problem

05.06.2008 17:58 - Ernad Husremović

Status:	Zatvoreno	Početak:	05.06.2008
Prioritet:	Normalan	Završetak:	
Odgovorna osoba:	Ernad Husremović	% završeno:	100%
Kategorija:		Procjena vremena:	0.00 sat
Ciljna verzija:			
Opis			
http://apcmag.com/vista_sp1_wont_install_on_dualboot_systems_microsoft.htm			

Historija

#1 - 05.06.2008 18:03 - Ernad Husremović

- Fajl EasyBCD_1.7.2.exe dodano

<http://iansblog.jandi.co.nz/2008/05/vista-sp1-easybcd-repairing-ubuntu.html>

Anyway I then decided I would first attempt Ubuntu working and then Vista.

So I booted using Ubuntu 7.10 CD and typed the following from a shell prompt:

- sudo -s
- ls -l /dev/sd* (to try and find my partitions)
- mkdir /a
- mount /a /dev/sda6 (I had to try a few until I got the right one)
- grub-install --root-directory=/a /dev/sda (note the drive here, not the partition)

I then rebooted and my Ubuntu was all back to normal. At least I had a working machine now. My Vista appeared on the grub menu and selected it but the machine just locked.

Back into Ubuntu and looking around I read this support page from EasyBCD. So I downloaded the Vista recovery DVD by going to this page.

Ran that, selected install, and then repair and Vista worked fine. What's more it didn't blow away Grub which really surprised me.

So now have a fully functioning system again. What a relief.

#2 - 20.06.2008 09:14 - Ernad Husremović

ma ovo je ludnica, vista na mraka-2 svaki put kada se boot-a setuje svoju /dev/sda1 particiju aktivnom, a linux particiju /dev/sda3 deaktivira ludara :(

pokušao sam prema gornjim dokumentima instalirati stari vista bootloader:

- pokrenuo vista oem install dvd
- ušao urecovery mode
- windows shell
- tamo pokrenuo:

```
BootRec /FixBoot /FixMbr
```

ali sistem se i dalje isto ponaša, mijenja aktivnu particiju ...

#3 - 20.06.2008 09:18 - Ernad Husremović

- Status promijenjeno iz Dodijeljeno u Zatvoreno

- % završeno promijenjeno iz 0 u 100

onda sam nadošao na workaround:

1. sa EasyBCD programom dodao ubuntu boot stavku
2. podesio da je timeout 7 sec
3. podesio da je default boot stavka ubuntu

takođe u grub-u podesio timeout na 7 sec

sistem uvijek prvo uđe u vista bootloader i tu ide na ubuntu nakon 7 sec ako ne odaberemo windows kada uđemo u grub procedura je standardna, kao što je i ranije bilo:

- odabiremo jedan od linux-a ili idemo na solaris grub

ovo je ipak workaround, zato što ako u grub-u odaberemo da je vista default stavka, on će se vrtiti u krug dok ne odaberemo nešto ručno ... ali meni to konkretno nije neki problem, s obzirom da mi je linux uobičajeno default boot stavka

#4 - 12.11.2008 15:59 - Ernad Husremović

ovaj EasyBCD je jedna od aplikacija paketa Tweak VI (tweak vista) - freeware

Fajlovi

EasyBCD_1.7.2.exe	741 KB	05.06.2008	Ernad Husremović
-------------------	--------	------------	------------------